

List of field-codes, data-elements, syntax, contents and example

Field-code	Data-element	Syntax	Contents	Examples
AC	Activity	Char*3	See code list	//AC/HAU//
AD	Address destination	Char*3	3-Alpha code (ISO-3166)	//AD/RUS//
AF	Apparent infringement			
AI	Assigned inspectors	Char*3 Num*4	3-Alpha code (ISO-3166) 1-9999	//AI/NOR333// or //AI/NLD4425 CEC29 RUS12//
AP	Cumulative production			
CA	Catch (or weekly catch)	Char*3 Num*7	See code list (FAO) 0-9999999	//CA/REB678// or //CA/RED2300 ORY200 BSF4500 HAD0//
CC	Cumulative catch	Char*3 Num*6	See code list (FAO) 0-999999	//CC/COD255// or //CC/PRA0 POL23 ORY356//
CD	Daily catch			
CO	Course	Num*3	1-360	//CO/270// (= heading 270°)
CS	Coastal state	Char*3	3-Alpha code (ISO-3166)	//CS/FRO//
DA	Date	Num*8	YYYYMMDD	//DA/20050131//
DF	Days fished	Num*3	1-365	//DF/7//
ED	End date	Num*8	YYYYMMDD	//ED/20051231//
ER	End record			//ER//
FO	Fishing operations			
FR	From	Char*3	3-Alpha code (ISO-3166)	//FR/ISL//

List of field-codes, data-elements, syntax, contents and example

Field-code	Data-element	Syntax	Contents	Examples
FS	Flag State	Char*3	3-Alpha code (ISO-3166)	//FS/NLD//
GE	Fishing gear	Char*3	See code list (FAO)	//GE/OTB// or //GE/PS2//
HA	Hails			
IR	Internal reference number	Char*3 Num*9	3-Alpha code (ISO-3166) 0-999999999	//IR/DEU009876//
IS	Date of issuing	Num*8	YYYYMMDD	//IS/20050122//
IV	Radio call sign	Char*7	IRCS	//RC/MGDD4//
KG	Transferred species	Char*3 Num*7	See code list (FAO) 0-9999999	//KG/WHB444500// or //KG/HER45600 MAC500//
LA	Latitude	Char*5	N(S)DDMM	//LA/N4533// or //LA/S2344//
LB	Log book			
LG	Longitude (decimal)	Char*8	+(-)DDD.ddd	//LG/-044.174// or //LG/+166.000//
LO	Longitude	Char*6	E(W)DDDMM	//LO/W04411//or //LO/E16600//
LT	Latitude (decimal)	Char*7	+(-)DD.ddd	//LT/45.544// or //LT/-23.743//
LU	Limited authorisation	Char*1	“Y” or “N”	//LU/N//
MA	Master name			
ME	Mesh size			
MI	Means of surveillance	Char*3	See code list	//MI/VES//

List of field-codes, data-elements, syntax, contents and example

Field-code	Data-element	Syntax	Contents	Examples
MS	Free text	Char*255	ISO 8859.1 characters	//MS/captain contacted refused boarding//
NA	Name	Char*30	ISO 8859.1 characters	//NA/SEA LION 7//
NE	Unit weight			
NU	Number of units			
OB	Quantity onboard	Char*3 Num*7	See code list (FAO) 0-9999999	//OB/MAC0// or //OB/WHB278400 HER45800//
OI	Object identification	Char*7	IRCS	//OI/V3RT7G//
ON	Observer name			
OS	Observation serial number	Num*3	0-999	//OS/023//
PD	Predicted date	Num*8	YYYYMMDD	//PD/20051030//
PH	Photography	Char*1	“Y” or “N”	//PH/Y//
PO	Port name (of registration or port of landing)	Char*20	ISO 8859.1 characters	//PO/BERGEN//
PR	Product form code			
PT	Predicted time	Num*4	HHMM	//PT/2345//
QP	Quantity produced			
RA	Relevant area	Char*6	See code list	//RA/XIVb//
RC	Radio call sign	Char*7	IRCS	//RC/MGDD4//

List of field-codes, data-elements, syntax, contents and example

Field-code	Data-element	Syntax	Contents	Examples
RD	Record date	Num*8	YYYYMMDD	//RD/20050131//
RE	Return error number	Num*3	0-999	//RE/101//
RJ	Catch discarded			
RN	Record number	Num*6	0-999999	//RN/12345//
RQ	Inspection requirement			
RT	Record time	Num*4	HHMM	//RT/0955//
RR	Regulated resources	Char*3	See code list (FAO)	//RR/WHB//
RS	Return status	Char*3	“ACK” or “NAK”	//RS/ACK//
SD	Start date	Num*8	YYYYMMDD	//SD/20010201//
SN	Species name	Char*3	See code list (FAO)	//SN/MAC//
SP	Speed	Num*3	Knots * 10	//SP/105// (= speed of 10.5 knots)
SQ	Sequence number	Num*6	0-999999	//SQ/234//
SR	Start record			//SR//
TF	Transhipped from	Char*7	IRCS	//TF/UABC//
TI	Time	Num*4	HHMM	//TI/0955//
TM	Type of message	Char*3	See code list	//TM/CAT//
TN	Trip number	Num*3	1-999	//TN/5//
TP	Vessel type	Char*3	See code list	//TP/LL// or //TP/TTF//

List of field-codes, data-elements, syntax, contents and example

Field-code	Data-element	Syntax	Contents	Examples
TT	Transhipped to	Char*7	IRCS	//TT/TXYZ//
TU	Transmission used			
TY	Type of packing			
US	Undersize			
VC	Vessel charterer	Char*60	ISO 8859.1 characters	//VC/SEAGULL SA CORUÑA ESPAÑA//
VL	Vessel length	Char*2 Num*3	“OA” or “PP” 0-999	//VL/OA64//
VO	Vessel owner	Char*60	ISO 8859.1 characters	//VO/MARPESCA PO BOX 66 HULL UK//
VP	Vessel power	Char*2 Num*5	“HP” or “KW” 0-99999	//VP/HP2345//
VT	Vessel capacity	Char*2 Num*4	“LC” or “OC” 0-9999	//VT/LC567//
XR	External registration	Char*14	ISO 8859.1 characters	//XR/3CO2399//
YM	Year and month	Num*6	YYYYMM	//YM/200412//
ZO	Zone	Char*3	3-Alpha code (ISO-3166)	//ZO/GRL//

ISO 8859.1 characters

3-Alpha codes (ISO-3166)

0-999999999